

SF30/C firmware revision history

Firmware version	Change log	Description	Hardware revision	Release date
1.11.2	LightWare Studio enhanced compatibility to include the following parameters: <ul style="list-style-type: none"> • USB Update rate • Serial update rate • Analog update rate 	Improvement/ features added	3/4	19/02/2021
1.11.1	Added: <ul style="list-style-type: none"> • Zero offset parameter 	Improvement/ features added	3, 4	07/11/2019
1.10.0	Added: <ul style="list-style-type: none"> • High power mode option now persists through restarts 	Minor	3, 4	13/09/2019
1.9.0	Added: <ul style="list-style-type: none"> • High power optional mode 	Improvement/ features added	3, 4	09/09/2019
1.8.0	Added: <ul style="list-style-type: none"> • Lost signal confirmations 	Improvement/ features added	3, 4	14/08/2019
1.7.2	Added: <ul style="list-style-type: none"> • LWNX parameter to change distance output mode 	Improvement/ features added	4	14/06/2019
1.7.1	Fixed: <ul style="list-style-type: none"> • Last return mode now uses first TDC stop correctly 	Minor	3, 4	14/05/2019
1.7.0	Added: <ul style="list-style-type: none"> • Last pulse return mode Changed: <ul style="list-style-type: none"> • Menu spacing is now spaces instead of tabs 	Improvement/ features added	3, 4	30/04/2019
1.6.1	Added: <ul style="list-style-type: none"> • Menu option for breakdown adjustment 	Improvement/ features added	3, 4	26/03/2019
1.6.0	Added: <ul style="list-style-type: none"> • Filtering modes for different sample rates • Breakdown offset • Comparator offset saving Changed: <ul style="list-style-type: none"> • Ignore results less than 0 m 	Improvement/ features added	3, 4	26/03/2019
1.5.1	Added: <ul style="list-style-type: none"> • Exposed analogue max range' to LWNX protocol 	Improvement/ features added	3, 4	07/02/2019

1.5.0	<p>Added:</p> <ul style="list-style-type: none"> Serial command interface <p>Changed:</p> <ul style="list-style-type: none"> Reject invalid TDC results more carefully Removed averaging on less than 128 shots per reading mode Pre-amp control loop response formula Shifted bias pump start time 	Improvement/ features added	3, 4	23/01/2019
1.4.2	<p>Added:</p> <ul style="list-style-type: none"> Option to enable reading synchronisation output 	Improvement/ features added	3, 4	11/12/2018
1.4.0	<p>Added:</p> <ul style="list-style-type: none"> Alarm functionality LWNX switching to serial port 	Improvement/ features added	3, 4	30/08/2018
1.3.1	<p>Added:</p> <ul style="list-style-type: none"> Analogue output in LWNX mode 	Improvement/ features added	3, 4	23/08/2018
1.3.0	Support for R4 hardware	Improvement/ features added	4	22/08/2018
1.1.0	<p>Decreased limit on maximum analogue output range</p> <p>Updated analogue range HMI message to show voltage range</p>	Improvement/ features added	3	28/06/2018
1.0.0	Initial release.	Initial release	3	13/06/2018